

List of Authorities



Values available:

*CDM	Authorized to work in a CDM session. This authority can be granted in Write and/or Read mode.
*LDMGEN	Authorized to use the Generate LDM option of the LDM menu in an LPM session. This authority only applies to the environment (*REPOSITORY).
*LDM	Authorized to work on the options of the LDM menu of an LPM session, except on the Generate LDM option. This authority can be granted in Write and/or Read mode.
*PDM	Authorized to work on options of the PDM menu in an LPM session: <ul style="list-style-type: none"> At the environment level, authorized to generate the PDM of public logical entities, accesses, and join entities, and to generate the field reference file. At the application area level, authorized to generate the PDM of private logical entities, accesses, and join entities of the application area.
*OPPM	Authorized to work in the Object manager and 4GL sessions. This authority can be granted in Write and/or Read mode.
*EXC	Authorized to use the Exchanges option from the Utilities submenu in the context-sensitive menu for environments , for sending and reception procedures. This authority only applies to the environment (*REPOSITORY).
*SEND	Authorized to use the Exchanges option from the Utilities submenu in the context-sensitive menu for environments , for sending procedures only (receptions are not allowed). This authority only applies to the environment (*REPOSITORY).
*TRANSL_A DM	Authorized to use all Translation manager functions (manager administration authority). This authority only applies to the environment (*REPOSITORY).
*TRANSL	Authorized to perform translation operations for the constants, messages and help topics in the current environment, excluding their management in the Translation manager . This authority only applies to the environment (*REPOSITORY).
*INSTALL	Authorized to access the Installation program manager . This authority can be granted in Write and/or Read mode. It only applies to the environment (*REPOSITORY).
*ADM_VER_ MAN	This authority lets you maintain a version manager . An administrator can grant this authority to a software engineer in a production, correction or development environment, at repository level (*REPOSITORY). It is automatically granted to the administrator who orders the building of a version manager from a 'simple' environment (i.e. one that is not part of a version manager).
*VAL_COR	This authority lets you validate corrections . An administrator can grant this authority to a software engineer in a correction environment, at repository level (*REPOSITORY). Corrections can only be validated in a correction environment. This authority only applies to correction environments.
*ADM_QUAL	Authorizes the modification of quality manager configuration. This right is only present at the environment level (*REPOSITORY).
*PROD_QU AL	Authorizes analyses to be launched on projects to produce their quality data. This right is only present at the environment level (*REPOSITORY).
*REP	Authorized to modify objects attached to an application area, where the software engineer is not the owner of the objects concerned.

Click below for further information on how to:

- [Modify authorities.](#)
- [Work with sessions.](#)